

# ESET Tech Center

Knowledgebase > ESET Endpoint Encryption > Removing DESlock+ from a workstation

---

## Removing DESlock+ from a workstation

Anish | ESET Nederland - 2018-01-24 - Comments (0) - ESET Endpoint Encryption

Sometimes you may need to completely remove DESlock+ from a system because it is being replaced. The instructions below describe this process for standalone or managed systems.

### 1. Decrypt data on the system

#### Granular Data

**Note:** If the system is to be used again after reinstalling or possibly by another user with the same encryption keys then this step may not be required. If this is the case and the system is not managed by an Enterprise Server you should ensure you take a backup of the key-file as detailed here: [How do I backup my Key-File?](#)

#### Encrypted Folders

Right click on the Encrypted Folder.  
Click **DESlock+\Decrypt Folder with DESlock+...**  
Follow the steps through the wizard to create a decrypted copy.  
If the check box **Leave encrypted backup** is cleared on the final page of the wizard the encrypted copy will be removed automatically.  
Alternatively the folder with the name ending **(DLP Backup)** can be deleted manually once you are happy the data has decrypted successfully.

#### Encrypted Files

Right click the Encrypted File.  
Click **DESlock+\Decrypt file with DESlock+...**  
If you want the original file deleted automatically click **Yes** to the offer to **delete the encrypted version** when offered.  
Alternatively click **No** and delete the encrypted version once you are happy the decryption has happened successfully.

#### Encrypted Archives

Open the Encrypted Archive.

Right click the archive name in the tree and then click **Extract Archive**.  
Select a destination path and click **OK** to extract the archive contents.  
Once you have verified the extracted folder contains the files you require  
the archive can be deleted.

## Virtual Disks

Mount the virtual disk and copy any data you require from it  
Right click the DESlock+ tray icon.  
Click **Virtual Disks\Virtual Disk Manager**.  
Select the virtual disk in the list, click **Unmount** if it is currently mounted.  
Click **Delete**.  
Click **Delete**.

## Removable Media

If the removable media is encrypted in file mode then you should first  
ensure you copy any required data from the encrypted folder as the  
removal process will delete it.  
Right click the DESlock+ tray icon.  
Click **Removable Media\Removable Media Encryption**.  
Select the encrypted disk in the drive list.  
Click the **Decrypt** or **Remove** button.  
If the device was encrypted with file mode you will be prompted that all  
encrypted files will be deleted.  
If the device was encrypted with full disk encryption mode decryption will  
commence. You will need to wait until decryption has completed to use the  
device again.

**Note:** If you have any encrypted optical media that you require access to again  
then you should take plain copies of the data before removing DESlock+.

## Full Disk Encryption

### Standalone

Login to DESlock+.  
Right click on the DESlock+ tray icon.  
Click the **Full Disk Encryption\Full Disk Encryption** item.  
Click **Manage Disks**.  
Select the disk or partition to decrypt then click the **Decrypt** button.  
Enter the FDE admin password then click **OK** to commence decryption. This  
will have been saved when you originally encrypted the machine. Please  
see here for details: [Why do I need an admin password?](#)  
The system can be used as normal while decryption is progressing. If the

machine is a laptop ensure that power is connected to prevent decryption from pausing. You should also ensure any power saving settings are disabled temporarily to ensure decryption finishes if the machine is left unattended.

### Managed by an Enterprise Server

Login to the Enterprise Server.

Select the **Workstation** in the list of workstations

Click the **Details** button.

Verify that the **WorkstationID** value displayed matches with the Workstation ID on the client. To find the Workstation ID on the client see this article: [How do I find my Workstation ID?](#)

Click the **Full Disk Encryption** button.

Click **Decrypt** next to the disks you wish to decrypt.

Click the **Decrypt** button in the lower right corner of the dialog.

The command will be received automatically over time, to speed up the process see this guide: [How do I manually synchronise the Enterprise Server and DESlock+ client?](#)

The system can be used as normal while decryption is progressing. If the machine is a laptop ensure that power is connected to prevent decryption from pausing. You should also ensure any power saving settings are disabled temporarily to ensure decryption finishes if the machine is left unattended.

Wait for the decryption process to complete fully and the status of the workstation to return to not encrypted in the Enterprise Server.

## 2. Deactivate users of the machine (Managed clients)

This step is only required by workstations managed by an Enterprise Server.

Login to the Enterprise Server.

Select the **Users** branch in the left hand navigation tree.

Select the user in the list of users in the Enterprise Server.

Click the **Details** button.

Select the **Workstations** tab.

Select the machine that is being refreshed in the list of Workstations.

Click the **Deactivate** button.

Set the **Are you sure you want to deactivate this user?** checkbox to confirm the operation.

Click the **Deactivate** button.

Login to the Windows profile of each user being deactivated and click the Enterprise Sync button as detailed previously.

This above process should be repeated for all users of the machine.

**Note:** If the user has been deactivated from all the machines they use they will

still be using a licence on the Enterprise Server indicated by their icon being blue in colour. If they will no longer require a licence this can be resolved by revoking the users licence from the Enterprise Server.

Select the **Users** branch in the left hand navigation tree.

Select the user in the list of users in the Enterprise Server.

Click the **Details** button.

Click the **Revoke licence** button.

If a message appears detailing that the user only has a single licence, click **OK**, click **Close**, ensure the correct user is selected, click **Delete**, confirm your Enterprise Server password to delete the user.

### 3. Uninstall software

Uninstall the software using the Windows Programs and Features control panel as detailed here: [Uninstalling DESlock+](#)

Keywords: decommission, destroy, migrate