

ESET Tech Center

Kennisbank > Legacy > Legacy ESET Remote Administrator (6.x / 5.x / 4.x) > 6.x > Configure ESET Remote Administrator to automatically deploy ESET endpoint products to unprotected computers (6.x)

Configure ESET Remote Administrator to automatically deploy ESET endpoint products to unprotected computers (6.x)

Ondersteuning | ESET Nederland - 2017-12-05 - Reacties (0) - 6.x

<https://support.eset.com/kb3702>

Issue

Configure a dynamic group that identifies client computers not protected by ESET endpoint products

Configure an automated task to deploy ESET endpoint products to unprotected computers

Solution

Permissions changes in ESET Remote administrator 6.5 and later

Before proceeding, please note important changes to user access rights and permissions in the latest versions of ESET Remote Administrator.

[View Permissions Changes](#)

I. Create New Dynamic Group

A user must have the following permissions for their home group:

Functionality	Read	Use	Write
Groups & Computers	✓	✓	✓

Once these permissions are in place, follow the steps below.


1. [Open ESET Remote Administrator Web Console](#) (ERA Web Console) in your web browser and log in.
2. Click **Computers** .
3. Select the parent static group that you want the new group to be under, click the gear icon and then select **New Dynamic Group** from the context menu.



Figure 1-1

Click the image to view larger in new window

4. Type a name for the group into the **Name** field. If necessary, configure the **Description** and **Parent Group** settings to your preferences.



Figure 1-2

Click the image to view larger in new window

5. Expand **Template** and click **New**.



Figure 1-3

Click the image to view larger in new window

6. Type a name into the **Name** field.



Figure 1-4

- 7. Expand **Expression**, select **NOR (All conditions have to be false)** from the **Operation** drop-down menu and then click **Add Rule**.



Figure 1-5

Click the image to view larger in new window

- 8. Expand **Installed software**, select **Application name** and then click **OK**.



Figure 1-6

- 9. Select **has prefix** from the drop-down menu, enter **ESET Endpoint** or **ESET File** (depending on which product you want automatically deployed to client workstations in this dynamic group) and then click **Finish**.



Figure 1-7

- 10. Click **Finish** and proceed to part II.

II. Create a new Client Task to deploy ESET endpoint products to unprotected clients

A user must have the following permissions for each affected object:

Functionality	Read	Use	Write
Groups & Computers	✓	✓	✓

A user must have the following permissions for their home group:

Functionality	Read	Use	Write
Software Install (under Client Tasks)	✓	✓	✓

Once these permissions are in place, follow the steps below.


1. Click **Admin**  → **Client Tasks**.
2. Expand **ESET Security Product**, select **Software Install** and then click **New**.



Figure 2-1

Click the image to view larger in new window

3. Type a name for the task into the **Name** field (configure the other settings in the **Basic** section as necessary).
4. Expand **Settings**, select the check box next to **I agree with application End User License Agreement** and then click **Choose ESET License**. Please note that **you will add Targets after the task is created**.

ESET Remote Administrator version 6.2.11 and earlier:

Adding targets is done during task creation (for example, after adding a new task and giving it a **Name**, click **Target** to add groups or clients to the task).



Figure 2-2

Click the image to view larger in new window

5. Select a valid license and click **OK**.
6. Click **Choose Package**.
7. Select the product you want to deploy and click **OK**.



Figure 2-3

Click the image to view larger in new window

8. Click **Finish** when you are finished making changes to your task.
9. Click **Create Trigger** when you are asked whether you want to

add a trigger for the client task.



Figure 2-4

10. Expand **Targets**. Click **Add groups** and select the check box next the dynamic group you created in part I. Click **OK**.



Figure 2-5

Click the image to view larger in new window

11. Expand the **Trigger** section and select **Joined Dynamic Group Trigger** from the **Trigger Type** drop-down menu.



Figure 2-6

Click the image to view larger in new window

12. Click **Finish**.



Figure 2-7

Click the image to view larger in new window

Tags
Endpoint
ERA 6.x