

# ESET Tech Center

[Knowledgebase](#) > [ESET PROTECT On-prem](#) > [Migrate ESET PROTECT from Virtual Appliance to Windows Server](#)

## Migrate ESET PROTECT from Virtual Appliance to Windows Server

Steeff | ESET Nederland - 2021-01-15 - [Comments \(0\)](#) - [ESET PROTECT On-prem](#)

### Issue

- Migrate ESET PROTECT Server from ESET PROTECT Virtual Appliance to Windows Server

### Prerequisites:

- ESET PROTECT Virtual Appliance
- New MySQL database using the default name “**era\_db**” and username “**root**”.




#### Supported MySQL Database

The following guide is only applicable to ESET PROTECT running a [supported](#) MySQL database.

### Solution

1. Generate a new ESET PROTECT Server certificate with connection information for the new ESET PROTECT Server. Log in to your existing ESET PROTECT Virtual Appliance (ESET PROTECT VA) and click **More** → **Peer Certificates** → **New** → **Certificate**.



2. Type the **Description** of the certificate. Select **Server** from the **Product** drop-down menu. Leave the **Host** field set to the default value (an asterisk) and leave the **Passphrase** and **Confirm passphrase** fields empty.

**eset PROTECT**

Computer Name QUICK LINKS HELP ADMINISTRATOR LOGOUT

DASHBOARD COMPUTERS DETECTIONS

Reports Tasks Installers Policies Notifications Status Overview More

**Create Certificate**  
Peer Certificates > New Server Certificate

**Basic**  
Sign Summary

**Description**  
New Server Certificate

**Tags**  
Select tags

**Product**  
Server

**Host**  
+

**Passphrase**  
Confirm passphrase  
Show passphrase

**Attributes (Subject)**  
Common name

BACK CONTINUE FINISH CANCEL

- Click **Sign**. Select the radio button next to **Certification authority** under **Signing method**. In the **Certification authority** options, click **Select certification authority**. A new window will open; select the certification authority you want to use to sign a new certificate. Click **OK** to confirm and return to the previous window.
- Type the **Certification Authority passphrase**. In this case, it is the same password you use to log into ESET PROTECT Appliance management console. Click the **Summary** section to review the settings of the new certificate and click **Finish** to apply.

**eset PROTECT**

Computer Name QUICK LINKS HELP ADMINISTRATOR LOGOUT

DETECTIONS Submitted Files Exclusions Quarantine

COMPUTERS Computer Users Dynamic Group Templates

LICENSES License Management

ACCESS RIGHTS Users

Permission Sets

CERTIFICATES Peer Certificates Certification Authorities

SERVER Server Settings

ACTIVITY AUDIT Audit Log

**Create Certificate**  
Peer Certificates > New Server Certificate

**Basic**  
Sign Summary

**Signing method**  
Certification authority Custom pfx file


**Certification authority**  
ESET Certification authority Create Certification Authority

**Custom pfx file**  
Choose File No file chosen UPLOAD


**Certification Authority passphrase**  
Show certification authority passphrase

BACK CONTINUE FINISH CANCEL

- Create a new policy to set a new ESET PROTECT Server IP address and assign the policy to all client computers. Click **Policies** → **New Policy**.




6. Enter a name for your policy, the **Description** field is optional. Click the **Settings** tab, select **ESET Management Agent** from the drop-down menu and then click **Edit server list**.




7. In the **Servers** window, click **Add**. In the host field, type the IP address of your new ESET PROTECT VA in format xxx.xxx.xxx.xxx. If you are using a port other than the default ESET PROTECT Server port 2222, specify your custom port number. Click **OK**. Make sure your new ESET PROTECT Server address is listed first and click **Save**.




8. Click the **Assign** tab to specify the clients that are targeted by this policy. Click **Assign** to display a new popup window with all Static and Dynamic Groups




9. Select the Static Group **All** to assign the policy to all connected agents and click **OK**.



10. Review the settings for this policy and click **Finish** to apply. The time to apply the policy will vary depending on your ESET PROTECT VA configuration.
11. When the policy is applied, [open ESET PROTECT VA Management Console](#) and create a [database backup](#).
12. In the ESET PROTECT Server Appliance management mode menu, select **Enable/Disable Webmin interface** to enable the [Webmin interface](#). Connect to the Webmin interface using a web browser with the IP address of ESET PROTECT VA and port 10000. A sample address is included here: <https://xxx.xxx.xxx.xxx:10000> Log into the Webmin interface using the ESET PROTECT VA credentials where **root** is the login.



13. In the Webmin interface main menu, expand **Others** and select **File Manager**. Navigate to the folder **/root/**. Right-click **era-backup.sql** file and select **Download** from the context menu. Save the file to a local drive and then copy it to a location accessible from the target Windows machine.



14. Return to the ESET PROTECT VA window, log into the management mode and select **Shut down system**.
15. On the target Windows Server, prepare a [clean installation of MySQL Server](#). When you are prompted by MySQL installer to create a Root Account Password, we recommend that you use the same one you used in ESET PROTECT Server Appliance.
16. Before proceeding you must import ESET PROTECT VA database backup to an empty database named *era\_db* on the target MySQL Server. Open a Command prompt and navigate to the MySQL Server binaries folder (default location is *C:\Program Files\MySQL\MySQL Server x.x\bin*). Enter the following commands, replace *TARGETHOST* with the address of the target database server.

```
mysql --host TARGETHOST -u root -p "--execute=CREATE DATABASE era_db /*!40100
DEFAULT CHARACTER SET utf8 */;"
```

17. Restore the ESET PROTECT VA backed up database to the previously prepared empty database. Make *PATHTOBACKUPFILE* the location where you have stored the ESET PROTECT VA database backup:

```
mysql --host TARGETHOST -u root -p era_db < PATHTOBACKUPFILE
```

18. Create an ESET PROTECT database user named *root* on the target MySQL server. Replace *TARGETERAPASSWD* with the password you used to log in to ESET PROTECT VA management console:

```
mysql --host TARGETHOST -u root -p "--execute=CREATE USER root@'%' IDENTIFIED BY
'TARGETERAPASSWD';"
```

19. Grant proper access rights for the ESET PROTECT database user - *root*, on the target MySQL server:

```
mysql --host TARGETHOST -u root -p "--execute=GRANT ALL ON eradb.* TO root;"
```

20. *tbl\_authentication\_certificate* table (if you do not remove these records, Agents may fail to connect to the new ESET PROTECT Server):

```
mysql --host TARGETHOST -u root -p "--execute=DELETE FROM
era_db.tbl_authentication_certificate where certificate_id = 1;"
```


21. Click [here](#) to download the ESET PROTECT Server stand-alone component. Execute the installation file and follow the Installation Wizard. When you reach the **Database server connection** setup in installation, make sure that the MySQL Server and MySQL ODBC Driver are detected properly. The database must be named *era\_db*. In the **Database account** section, type in the **Username** "root" and **Password** you have created in step 18. Click **Next** to continue. The installer will ask if you want to use the provided user *root* as a database user for ESET PROTECT, click **Yes** to apply and continue.

The screenshot shows the 'Database server connection' window of the ESET PROTECT Server Setup. The window has a title bar with the ESET logo and standard window controls. The main area contains several input fields: 'Database' (MySQL Server), 'ODBC driver' (MySQL ODBC 5.3 Unicode Driver), 'Database name' (era\_db), 'Hostname' (localhost), and 'Port' (3306). Below these is the 'Database account' section with 'Username' (root) and 'Password' (masked with dots). The 'Next' button is highlighted with a blue border, and the 'Back' and 'Cancel' buttons are also visible.

22. In the following window, the Installation Wizard will configure an Administrator password for Web Console. Select the check box next to **Use Administrator password already stored in the database**. Change the Agent and Console port if required to match the settings in ESET PROTECT Server Appliance. The default value for Agent port is 2222 and the default value for Console port is 2223.

The screenshot shows the 'Web Console user & server connection' window of the ESET PROTECT Server Setup. The window has a title bar with the ESET logo and standard window controls. The main area contains a checkbox labeled 'Use Administrator password already stored in the database', which is checked. Below this are fields for 'Password' and 'Password confirmation'. At the bottom, there are fields for 'Agent port' (2222) and 'Console port' (2223). The 'Next' button is highlighted with a blue border, and the 'Back' and 'Cancel' buttons are also visible. A red arrow points from the checked checkbox to the 'Next' button.

23. In the following window, select the radio button next to **Keep currently used certificates** and click **Next** to continue. Follow the Installation Wizard to finish the Server component installation.



24. [Install](#) ESET PROTECT Web Console.
25. [Open ESET PROTECT Web Console](#) in your web browser and log in. Use your ESET PROTECT Server Appliance password. Verify that the agents have migrated successfully and are connecting to the new server. Do not uninstall your old ESET PROTECT Server Appliance until you have verified the migration was successful.