

# ESET Tech Center

Kennisbank > Endpoint Solutions > Enable or Disable ESET LiveGrid® in ESET Business Products (8.x - 9.x)


## Enable or Disable ESET LiveGrid® in ESET Business Products (8.x - 9.x)

Mitch | ESET Nederland - 2022-11-29 - Reacties (0) - Endpoint Solutions


### Solution

#### Enable LiveGrid on endpoints using ESET PROTECT

1. [Open the ESET PROTECT Web Console](#) in your web browser and log in.
2. Click **Policies**, select the policy for clients on which you want to enable ESET LiveGrid® and click the gear icon → **Edit**.



3. Click **Settings** → **Detection Engine** → **Cloud-based protection**.
4. Click **Enable ESET LiveGrid® reputation system (recommended)** to enable ESET LiveGrid®, or leave this setting deselected to disable ESET LiveGrid®.
5. Click **Finish** to apply your changes. Clients will receive the policy changes the next time that they check in to ESET PROTECT.




## Enable LiveGrid on endpoints using ESMC 7.x



If you do not use ESET Security Management Center to manage your network  
[Perform these steps on individual client workstations.](#)


1. [Open ESET Security Management Center Web Console](#) (ESMC Web Console) in your web browser and log in.
2. Click **Policies**, select the policy for clients on which you want to enable ESET LiveGrid® and click the gear icon > **Edit**.



3. Click **Settings** → **Detection Engine** → **Cloud-based protection**.

4. Click **Enable ESET LiveGrid® reputation system (recommended)** to enable ESET LiveGrid®, or leave this setting deselected to disable ESET LiveGrid®.

5. Click **Finish** to apply your changes. Clients will receive the policy changes the next time that they check in to ESET Security Management Center.



# Enable LiveGrid on endpoints using ERA




If you do not use ESET Security Management Center to manage your network [Perform these steps on individual client workstations.](#)

Version 5.x users: [Enable ESET Live Grid from ESET Remote Administrator \(5.x\)](#)

Version 6.x users:


1. Open ESET Remote Administrator Web Console (ERA Web Console) in your web browser and log in.
2. Click **Admin** → **Policies**.
3. Select the policy for clients on which you want to enable ESET LiveGrid® and click the gear icon → **Edit**.



4. Expand **Settings** → **Tools**.


5. Click **Enable ESET LiveGrid® reputation system (recommended)** to enable ESET LiveGrid®, or leave this setting deselected to disable ESET LiveGrid®.

6. Click **Finish** to apply your changes. Clients will receive the policy changes the next time that they check in to ESET Remote Administrator.



## Enable LiveGrid from ESET endpoint products

1. Open ESET Endpoint Security or ESET Endpoint Antivirus.
2. Press the **F5** key to access Advanced setup.
3. Expand **Detection Engine** → **Cloud-based protection**.
4. Select the check box next to **Enable ESET LiveGrid® reputation system** to enable ESET LiveGrid®, or deselect it to disable ESET LiveGrid®. Click **OK** to save your changes.





Enable or Disable ESET LiveGrid® in ESET Business Products




Later bekij...



Delen



Bekijken op  YouTube