

ESET Tech Center

Kennisbank > Endpoint Solutions > Enable or Disable ESET LiveGrid® in ESET Business Products (8.x - 9.x)


Enable or Disable ESET LiveGrid® in ESET Business Products (8.x - 9.x)

Mitch | ESET Nederland - 2022-11-29 - Reacties (0) - Endpoint Solutions


Solution

Enable LiveGrid on endpoints using ESET PROTECT

1. [Open the ESET PROTECT Web Console](#) in your web browser and log in.
2. Click **Policies**, select the policy for clients on which you want to enable ESET LiveGrid® and click the gear icon → **Edit**.



3. Click **Settings** → **Detection Engine** → **Cloud-based protection**.
4. Click **Enable ESET LiveGrid® reputation system (recommended)** to enable ESET LiveGrid®, or leave this setting deselected to disable ESET LiveGrid®.
5. Click **Finish** to apply your changes. Clients will receive the policy changes the next time that they check in to ESET PROTECT.




Enable LiveGrid on endpoints using ESMC 7.x



If you do not use ESET Security Management Center to manage your network
[Perform these steps on individual client workstations.](#)


1. [Open ESET Security Management Center Web Console](#) (ESMC Web Console) in your web browser and log in.
2. Click **Policies**, select the policy for clients on which you want to enable ESET LiveGrid® and click the gear icon > **Edit**.



3. Click **Settings** → **Detection Engine** → **Cloud-based protection**.

4. Click **Enable ESET LiveGrid® reputation system (recommended)** to enable ESET LiveGrid®, or leave this setting deselected to disable ESET LiveGrid®.

5. Click **Finish** to apply your changes. Clients will receive the policy changes the next time that they check in to ESET Security Management Center.



Enable LiveGrid on endpoints using ERA




If you do not use ESET Security Management Center to manage your network [Perform these steps on individual client workstations.](#)

Version 5.x users: [Enable ESET Live Grid from ESET Remote Administrator \(5.x\)](#)

Version 6.x users:


1. Open ESET Remote Administrator Web Console (ERA Web Console) in your web browser and log in.
2. Click **Admin** → **Policies**.
3. Select the policy for clients on which you want to enable ESET LiveGrid® and click the gear icon → **Edit**.



4. Expand **Settings** → **Tools**.


5. Click **Enable ESET LiveGrid® reputation system (recommended)** to enable ESET LiveGrid®, or leave this setting deselected to disable ESET LiveGrid®.

6. Click **Finish** to apply your changes. Clients will receive the policy changes the next time that they check in to ESET Remote Administrator.



Enable LiveGrid from ESET endpoint products

1. Open ESET Endpoint Security or ESET Endpoint Antivirus.
2. Press the **F5** key to access Advanced setup.
3. Expand **Detection Engine** → **Cloud-based protection**.
4. Select the check box next to **Enable ESET LiveGrid® reputation system** to enable ESET LiveGrid®, or deselect it to disable ESET LiveGrid®. Click **OK** to save your changes.





Enable or Disable ESET LiveGrid® in ESET Business Products




Later bekij...



Delen



Bekijken op  YouTube