

# ESET Tech Center

Knowledgebase > Legacy > How do I configure ESET Endpoint Security to use different firewall settings in different locations?

---

## How do I configure ESET Endpoint Security to use different firewall settings in different locations?

Ondersteuning | ESET Nederland - 2017-11-28 - Comments (0) - Legacy

<https://support.eset.com/kb3478>

### Issue

---

Create multiple Personal firewall profiles for use on different networks (for example, public WiFi or corporate LAN)

Automatically switch between profiles when you enter or leave a trusted network, subnet or LAN

Enable automatic switching for Personal firewall settings

### Details

### Solution

---

**If you use ESET Remote Administrator to manage your network**

[Perform these steps in ESET Remote Administrator.](#)

## Configure Endpoint Security to use different firewall settings on individual client workstations

- I. [Define your zone](#)
- II. [Create your Personal firewall profile](#)

## I. Define your zone

**Important! Perform these steps while in the zone you are adding**

To use the **Populate with selected connection settings** feature in step 6, you must be connected to the network that will be saved as a new zone.

1. [Open the main program window of your Windows ESET product.](#)
2. Press the **F5** key to open **Advanced setup**.
3. Click **Firewall**, expand **Advanced** and click **Edit** next to **Zones**.



**Figure 1-1**

**Click the image to view larger in new window**

4. Click **Add**, type a name for this zone into the **Name** field, type the IP address or subnet of the zone into the **Remote computer address** field and then click **OK** twice.



**Figure 1-2**

**Click the image to view larger in new window.**

5. To add additional zones, repeat steps 2-4 above. Continue to Part II to create your Personal firewall profile

## II. Create your Personal firewall profile

1. Open ESET Endpoint Security. [How do I open my ESET Product?](#)
2. Press the **F5** key to open **Advanced setup**.
3. Click **Firewall**, expand **Firewall Profiles** and click **Edit** next to **List of profiles**.



### Figure 2-1

**Click the image to view larger in new window**

4. In the **Firewall profiles** window, click **Add**, type a name for this profile into the **Name** field and then click **OK** to close the Add profile dialog.



### Figure 2-2

**Click the image to view larger in new window**

5. To add rules to the profile, expand **Advanced** and click **Edit** next to **Rules**. Click **OK** to close the rules editor window when you are finished.



### Figure 2-3

**Click the image to view larger in new window**

6. To assign the profile you created to an existing network, expand **Known Networks** and click **Edit** next to **Known Networks**. Select the network to which you want to apply the profile, click **Add** and then select your new profile from the **Firewall profile** drop-down menu.



### Figure 2-4

**Click the image to view larger in new window**

---

Related articles:

[How do I configure endpoints to use different update settings depending on the network they are connected to? \(6.x\)](#)

[How do I configure ESET Endpoint Security to use different firewall settings in different locations \(5.x\)](#)

Tags

