

# ESET Tech Center

[Knowledgebase](#) > [Legacy](#) > [Legacy ESET Remote Administrator \(6.x / 5.x / 4.x\)](#) > [6.x](#) > [Install ESET Rogue Detection Sensor on a different computer than ESET Remote Administrator Server \(6.x\)](#)

## Install ESET Rogue Detection Sensor on a different computer than ESET Remote Administrator Server (6.x)

Ondersteuning | ESET Nederland - 2025-03-07 - [Comments \(0\)](#) - [6.x](#)

<https://support.eset.com/kb3704>

### Issue

---

When using the ESET Remote Administrator (ERA) Virtual Appliance, you can install ESET Rogue Detection Sensor on a client computer to detect other clients that are not protected by ESET products

### Details

### Solution

---

#### Prerequisites

The computer on which you plan to install ESET Rogue Detection Sensor (ESET RD Sensor) must have the ESET Remote Administrator Agent (ERA Agent) installed. [Click here for step-by-step instructions to install the ERA Agent.](#)

The computer on which you plan to install RD Sensor must have [WinPcap](#) installed.

---

### Solution

1. Click the appropriate link below to download the ESET RD Sensor installer file.

[64-BIT DOWNLOAD](#)

[32-BIT DOWNLOAD](#)

2. Double-click the installer file (**RDSensor\_x64.msi** or **RDSensor\_x86.msi**).
3. Click **Next**.



**Figure 1-1**

4. Read the End User License Agreement. If you agree to the terms, select the check box next to **I accept the terms in the License Agreement** and then click **Next**.



**Figure 1-2**

5. Click **Next**.



**Figure 1-3**

6. Click **Install**.



**Figure 1-4**

7. Click **Finish**. Once the client computer checks into the ESET Remote Administrator Server (ERA Server), ESET RD Sensor on the client will begin reporting rogue computers to your ERA Server. [Click here for step-by-step instructions to add new computers to the ERA directory using ESET RD Sensor.](#)

---

## Related articles:

[Add client computers in ESET Remote Administrator \(6.x\)](#)

- Tags
- [ERA 6.x](#)