

# ESET Tech Center

Kennisbank > Legacy > Legacy ESET Remote Administrator (6.x / 5.x / 4.x) > 6.x > Install ESET Rogue Detection Sensor on a different computer than ESET Remote Administrator Server (6.x)

---

## Install ESET Rogue Detection Sensor on a different computer than ESET Remote Administrator Server (6.x)

Ondersteuning | ESET Nederland - 2017-12-05 - Reacties (0) - 6.x

<https://support.eset.com/kb3704>

### Issue

---

When using the ESET Remote Administrator (ERA) Virtual Appliance, you can install ESET Rogue Detection Sensor on a client computer to detect other clients that are not protected by ESET products

### Details

### Solution

---

#### Prerequisites

The computer on which you plan to install ESET Rogue Detection Sensor (ESET RD Sensor) must have the ESET Remote Administrator Agent (ERA Agent) installed. [Click here for step-by-step instructions to install the ERA Agent.](#)

The computer on which you plan to install RD Sensor must have [WinPcap](#) installed.

---

#### Solution

1. Click the appropriate link below to download the ESET RD Sensor installer file.

[64-BIT DOWNLOAD](#) [32-BIT DOWNLOAD](#)

2. Double-click the installer file

(**RDSensor\_x64.msi** or **RDSensor\_x86.msi**).

3. Click **Next**.



**Figure 1-1**

4. Read the End User License Agreement. If you agree to the terms, select the check box next to **I accept the terms in the License Agreement** and then click **Next**.



**Figure 1-2**

5. Click **Next**.



**Figure 1-3**

6. Click **Install**.



**Figure 1-4**

7. Click **Finish**. Once the client computer checks into the ESET Remote Administrator Server (ERA Server), ESET RD Sensor on the client will begin reporting rogue computers to your ERA Server. [Click here for step-by-step instructions to add new computers to the ERA directory using ESET RD Sensor.](#)

---

Related articles:

[Add client computers in ESET Remote Administrator \(6.x\)](#)

Tags

ERA 6.x