

# ESET Tech Center

Nieuws > Releases > Feature release > ESET Mail Security for Microsoft Exchange Server version 11.1.10008.0 has been released

---

## ESET Mail Security for Microsoft Exchange Server version 11.1.10008.0 has been released

2024-11-26 - Steef | ESET Nederland - Reacties (0) - Feature release

ESET Mail Security for Microsoft Exchange Server version 11.1.10008.0 has been released and is available [for download](#).

### Release details:

- Release date: 26th of November 2024
- Product: ESET Mail Security for Microsoft Exchange Server - 11.1.10008.0
- Type: Feature update
- Availability: Global excl. Japan

### Schedule for automatic updates:

- Phase one: 50% throttling, starts on the 10th of December 2024
- Phase two: 100% throttling, starts on the 17th of December 2024

### Changelog

- NEW: Mail quarantine integration with ESET PROTECT On-Prem.
- NEW: Quarantine reports can now be set up for administrators outside of the domain.
- NEW: Support for On-demand Vulnerability scan for Vulnerability and Patch Management.
- NEW: Vulnerability and Patch Management logging capability both locally and reporting to ESET.
- NEW: Authenticated received chain verification support.
- NEW: New macros available to use with rule "Send mail notification".
- NEW: RDP Access restriction feature.
- IMPROVED: Modification of body of Base64 encoded emails.
- IMPROVED: Brute force attack protection was extended to cover MS SQL and MySQL protocols.
- IMPROVED: Various Override mode modifications for better security and user

experience.

- IMPROVED: Support for URL analysis in document-reference headers.
- IMPROVED: Macros available for rules are now more unified and with better explanation.
- IMPROVED: Performance improvements of agent priority setting both in GUI and ESET Shell.
- IMPROVED: Local mailbox counting in domains with multiple sub-domains.
- CHANGED: ESET Mail Security now uses the Replay directory instead of Pickup directory on the Exchange Server to send internal notifications and reports.
- CHANGED: Emails sent to journaling mailboxes will not be quarantined.
- CHANGED: “Report a phishing site” was moved to setup/server for improved usability.
- FIXED: Incorrect display of sender’s IP address in SMTP protection logs.
- FIXED: Modification of subject of phishing messages now works when detected during the on-demand scan.

Please note, this feature update has impact on the support level status of previously released versions:

[^ ESET Mail Security for Microsoft Exchange Server](#)

Version	Original Release Date	Latest Build	Latest Build Release Date	Current Status	Full Support	Limited Support
11.1	November 26, 2024	11.1.10008.0	November 26, 2024	✔ Full Support	Until next feature update (minimum until November 30, 2025)	Until November 30, 2027
11.0	April 2, 2024	11.0.10008.0	June 18, 2024	✔ Full Support	Until April 30, 2025	Until April 30, 2027
10.1	September 19, 2023	10.1.10014.0	December 20, 2023	✔ Full Support	Until April 30, 2025	Until April 30, 2027
10.0	March 28, 2023	10.0.10018.1	February 14, 2024	⚠ Limited Support	Ended (September 19, 2023)	Until April 30, 2025

## Support resources

ESET provides support through a fully localized app and Online Help (user guides), online Knowledgebase, and applicable to your region, chat, email or phone support.

- [What is new in ESET Mail Security for Microsoft Exchange Server](#)
- [Key features for ESET Mail Security for Microsoft Exchange Server](#)
- [ESET Mail Security for Microsoft Exchange Server Online Help \(user guide\)](#) contains comprehensive reference information for system settings, configurations, installation scenarios and more.

For other questions, such as troubleshooting, FAQ and video tutorial, search [the ESET Knowledgebase](#).